

# Initial Install of ECE 400-Agent HA Configuration

## Contents

[Introduction](#)

[Prerequisites](#)

[Requirements](#)

[Components Used](#)

[Background](#)

[Terminology](#)

[Example Layout](#)

[Active Directory](#)

[User Accounts](#)

[Virtual Machines and Logical Resources](#)

[Drive Letters and Contents](#)

[File and Directory Objects](#)

[System Preparation](#)

[Download and Deploy the OVA Template](#)

[Install Windows Server on All 4 Servers](#)

[Format the 50 GB and 300 GB Disks on the Two Collocated Servers](#)

[Install SQL Server on the Two Collocated Servers](#)

[Preinstallation Steps](#)

[Step 1. Add Required Windows Features](#)

[Step 2. Prepare Active Directory](#)

[Create required Service Accounts](#)

[Prestage the Cluster Name Object \(CNO\)](#)

[Grant User Permissions](#)

[Grant CNO Permissions](#)

[Register SPN](#)

[Step 3. Create Required Directories](#)

[Create the shared directory](#)

[Create the SSIS directory](#)

[Create the SQL Server data and backup directories](#)

[Step 4. Configure Distributed File System](#)

[Create the Namespace](#)

[Add the Namespace Server](#)

[Add Folder and Folder Targets and Configure Replication](#)

[Configure Staging folder Quota](#)

[Test the DFS Namespace and Replication Group](#)

[Step 5. Configure Windows Server Failover Cluster](#)

[Initial Cluster Setup](#)

[Configure Cluster Quorum](#)

[Review Cluster](#)

[Step 6. Configure SQL Server](#)

[Enable SQL Server Availability Groups](#)

[Create a Temporary Database](#)

[Make a Full Database Backup After You Create the Database](#)

[Create the Availability Group](#)

[Verify Availability Group Setup](#)

[Update Dynamic DNS \(DDNS\) Configuration](#)

[Configuration Checkpoint](#)

[Install ECE](#)

[Step 1. Install ECE on VM-1A](#)

[Step 2. Install ECE on VM-1B](#)

[Step 3. Install ECE on VM-2A and VM-2B](#)

[Complete Post-Installation Tasks](#)

[Step 1. Assign Permissions to ECE Directories](#)

[Step 2. Start then Stop ECE Service on Collocated Servers](#)

[Step 3. Prepare Databases to Join the Availability Group](#)

[Step 4. Restore Database Backup on Side-B Server](#)

[Step 5. Join Databases to the Availability Group](#)

[Step 6. Validate Availability Group](#)

[Step 7. Run Reports DB Utility](#)

[Step 8. Fix SSIS Server Maintenance Job](#)

[Step 9. Schedule Database Backups](#)

[Step 10. Update Key Configuration Files](#)

[Patch ECE](#)

[Step 1. Prepare Servers to be Patched](#)

[Stage Patch File](#)

[Stop ECE Processes](#)

[Stop ECE](#)

[Step 2. Backup Servers](#)

[Backup SQL Databases](#)

[Backup Key Files](#)

[Step 3. Install Patch](#)

[Install patch on Side-A Collocated Server](#)

[Install patch on Side-B Collocated Server](#)

[Install patch on Side-A Web Server](#)

[Install patch on Side-B Web Server](#)

[Step 4. Post-patch Validation](#)

[Check and Update Key files](#)

[Merge Chat Template Changes](#)

[Start ECE](#)

[Log in to ECE Web Pages](#)

[Log in to Finesse and ECE Gadget](#)

[Start ECE Processes](#)

[Final Notes](#)

# Introduction

This document describes the initial installation of Enterprise Chat and Email (ECE) 400-agent High Availability (HA).

## Prerequisites

### Requirements

Cisco recommends that you have knowledge of these topics:

- Enterprise Chat and Email (ECE) 12.X
- Windows Server 2016
- SQL Server Enterprise edition 2016

### Components Used

The information in this document is based on these software versions:

- ECE 12.5(1)
- SQL Server 2016 Enterprise Edition
- Windows 2016

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

## Background

Enterprise Chat and Email 12.0 and later now support full, high-availability installation for both the 400-Agent and 1500-Agent deployments. The 1500-Agent deployment requires a total of 30 Virtual Machines (VMs) when installed in an HA configuration. Once the File Server and SQL Server Installation and configuration is done, the remainder of the install, follows the same order and steps as the 1500-Agent non-HA deployment did previously. The 400-Agent deployment only requires 4 total servers, but due to the shared nature of the collocated server, the installation requires careful deployment to ensure success. Almost all of the most critical steps are done prior to the actual installation of ECE. This article goes through what is required to do the full install from start to end.

## Terminology

Throughout this document, these terms are used.

- Windows Server Failover Cluster (WSFC) – This Microsoft Windows Server feature allows multiple physical servers to provide resiliency for the others. When you have multiple servers in a cluster, this does not remove functions or capabilities from any server that is not currently the primary node, it simply provides a way for the servers to know the status of the others. Each server can own one or more roles at any one time.

- **AlwaysOn Availability Groups (AG)** – This is a Microsoft SQL Server redundancy feature which gives a high level of protection to databases while minimizing the time required to move from one side or node to the other. Unlike the older, and now deprecated, Failover Cluster Instance, all SQL Server nodes in an Availability Group can be fully operational at all times and have a full copy of the database. When Microsoft SQL Server is deployed on Windows Servers, the Availability Group requires a Windows Server Failover Cluster to operate. There are several key terms related to AGs that you may see in this document.

**Instance** – An instance an independent SQL Server with its own executables and databases. A single physical server can host multiple instances of SQL Server.

**Replica** – A replica is a distinct instance in an AG. There are two types of replicas in an AG. **Primary Replica** – The Primary Replica, or just Primary, allows both read and write operations on the databases in the AG. There can only be one Primary replica in an AG. The primary replica is also the only replica that allows most database backup operations. **Secondary Replica** – All other nodes in the AG are referred to as Secondary Replicas or Secondaries. A **Readable Secondary** is a Secondary Replica that allows read operations against the databases but not write operations. Readable Secondaries allow a specific type of database backup called a copy-only backup. If a normal backup is attempted on a Secondary, an error message as follow is shown, "This BACKUP or RESTORE command is not supported on a database mirror or secondary replica."

**Listener** – A Listener is a component of the Availability Group. Whichever node is Primary owns the Listener. A Listener has at least one IP and port. If the nodes of the Availability Group are separated across different subnets, then the Listener must have valid IPs in each subnet to ensure availability. The Listener shows up as a Computer object in Active Directory.

**Availability Database** – An Availability Database is any database on a SQL Instance that has been joined to the AG. An Instance can also have databases which are not members of an Availability Group. These databases are normal SQL databases as far as read/write operations are concerned. When an instance is the Primary Replica, you may use the Listener name to access any local databases or resources, however when that server is no longer the Primary, access to the database must be done by use of the server name.
- **SQL Server Integration Services (SSIS)** – SSIS is a feature included with Microsoft SQL Server that allows for data clean-up, transformation, manipulation, and other data tasks at run-time. SSIS Packages allows developers to extract data from many data sources, then use scripts to load that data into one or more databases. ECE uses this functionality to copy data from the Active database into the Reports database on a regular basis.
- **Distributed File System (DFS)** – This add-on feature for Microsoft Windows Server allows multiple SMB file shares to be presented as a single entity. It also allows for the automatic synchronization and replication of files across servers.

There are two components that make up DFS. **DFS Namespaces** – A Namespace is a logical view of a share. One or more servers may host the files in the namespace, but the all access to the files is done by use of the network path to the namespace.

There are two types of namespaces. **Domain-based namespace** – A Domain namespace is accessed through the UNC path in the format, \\<domain>\<DFSRoot>. This type of Namespace gives the highest availability and is an object in the Active Directory tree. This is the only Namespace that ECE supports. **Standalone namespace** – A Standalone namespace is accessed through the UNC path in the format, \\<servername>\<DFSRoot>. While replication can be used to keep multiple servers in sync and ensure that they contain the same files, if the server that is the host of the namespace goes down, then the namespace

becomes unavailable. ECE does not support Standalone namespaces. DFS Replication – A DFS Replication group is a way to keep files across multiple physical servers in sync. There are several DFS terms which you may see in this document.

Namespace server – A namespace server hosts a namespace. Each namespace server contains a local path folder that contains the DFS root folders. Namespace local path – A directory that exists on each Namespace server. This directory must be separate from the directory which is shared into the namespace. Namespace root – This is the start point of the namespace. In a domain-based namespace, the root is the identifier that is immediately after the domain name. Each namespace root is represented by a physical folder that exists in the Namespace local path. Folder – Folders are used in one of two ways in the namespace. A folder with no Folder target is used to organize data into logical views. ECE does not use this type of folder. A folder with one or more Folder targets is used to present data to the user of the namespace. When a user or application navigates to this folder, DFS transparently redirects them to the mapped folder target. Folder Targets – A folder target is UNC path to a shared folder that contains the actual content. In ECE, the Folder targets are the ECE Shared directories which host the content that the File server role is responsible for.

- Service Principal Name – This is often abbreviated as SPN. You may hear this referred to as spin. The Service Principal Name is the unique identifier of a service instance. In ECE, when Windows Integrated Authentication is used to access the databases – as is required in an HA deployment, the SPN allows the SQL Server Service account to perform a proxy authentication to Active Directory on behalf of another account. When an ECE Service accesses the database, it does so through the ECE Service account. This account is then passed through to Active Directory for authentication and authorization.

## Example Layout

Throughout this document, a lab system is used for screenshots and example commands. This gives the details of the Active Directory domain, Usernames, and Machine names and IP addresses. The specific configuration items may be repeated later on in the document, closer to where they are used.

## Active Directory

- Fully qualified domain name: massivedynamic.com
- Pre-Windows 2000 domain: MASSIVE

## User Accounts

| Description                | Account Name |
|----------------------------|--------------|
| SQL Server Service account | SQLServerSvc |
| ECE Service Account        | ECESvc       |

## Virtual Machines and Logical Resources

| Identifier | Name/Value  | IP Addresses | Description       | ECE Roles                                 |
|------------|-------------|--------------|-------------------|---|
| VM-1A      | CC2K125ECEA | 14.10.162.   | Side-A collocated | File Server (DFS Node 1), Database (Avail |

|               |                  |  |                                    |  |
|---------------|------------------|--|------------------------------------|--|
|               | A                | 168  | server                             | Group Replica), Messaging, Services, Application   |
| VM-2A         | CC2K125ECE<br>WA | 14.10.162.<br>169                                    | Side-A web server                  | Web Server   |
| VM-1B         | CC2K125ECEA<br>B | 14.10.172.<br>168                                    | Side-B collocated server           | File Server (DFS Node 2), Database (Avail Group Replica), Messaging, Services, Application |
| VM-2B         | CC2K125ECE<br>WB | 14.10.172.<br>169                                    | Side-B web server                  | Web Server   |
| WSFC-CNO      | CC2K125ECE<br>OC | 14.10.162.<br>170<br>14.10.172.<br>170<br>14.10.162. | CNO for WSFC                       |  |
| Listener      | CC2K125ECE<br>B  | 161<br>14.10.172.<br>171                             | SQL AG Listener Name               |  |
| Listener Port | 1433             | N/A  | SQL AG Listener Port               |  |
| ECE-VIP       | ECE              | 14.10.162.<br>96                                     | Virtual IP for ECE on Loadbalancer |  |

## Drive Letters and Contents

| Drive Letter | Size  | Usage                              | Notes                                |
|--------------|-------|------------------------------------|--------------------------------------|
| C            | 80 GB | Windows OS, SQL Executables        | SQL Server not present on Web server |
| D            | N/A   | DVD Mount Point                    |                                      |
| E            | 50GB  | ECE Application and SSIS folder    | Drive not present on Web server      |
| F            | 300GB | SQL Database files and SQL Backups | Drive not present on Web server      |

## File and Directory Objects

This lists the file and directory objects that are referenced throughout the documentation. While the specific directory names are not mandatory, it is best to keep a common structure across all servers.

| Identifier         | Path                           | Description   | Notes   |
|--------------------|--------------------------------|---|---|
| Shared Directory   | E:\ECEFile                     | Directory on collocated servers that is the Folder target in the DFS Namespace.   | Does not exist on web server.                                       |
| ECE Home Directory | E:\ECE                         | Directory on all servers that ECE uses at run-time for application execution, temporary files, and logs.                | On web server only, ECE Home directory is on the C: drive.          |
| SSIS Directory     | E:\ssis_data                   | Directory on collocated servers where SSIS templates are stored and used as a temporary directory by the SSIS packages. |   |
| SQL Install        | C:\Program Files\Microsoft SQL | Directory on collocated servers where Microsoft SQL Server is installed.  | All system DBs, including TempDB and the SSISDB should remain on C: |

|                      | Server                            | C: drive with SQL executables.  |
|----------------------|-----------------------------------|---|
| SQL Data Directory   | F:\MSSQL\Data                     | Directory on collocated server where the 3 ECE databases are installed. |
| SQL Backup Directory | F:\MSSQL\Backups                  | Directory on collocated servers used for database backups.              |
| DFS Share            | \\massivedynamic.com\ECE_Root\ECE | Domain based DFS Namespace used for shared ECE files.                   |
| DFS Root             | ECE_Root                          | The root portion of the DFS Namespace.                                  |
| DFS Folder           | ECE                               | The folder that is shared in the DFS Root.                              |
| DFS Local path       | C:\DFSRoots                       | Folder on collocated servers where the DFS Root folder is stored.       |

## System Preparation

This must be done before you start the steps in the main body of this document.

### Download and Deploy the OVA Template

You need 2 VMs on each side, 1 web server and 1 collocated server. The OVA template identifies these VMs as follows.

#### Web Server

- Label: Web Server
- Details: (12.5 v1.0 OVA used, check current OVA for your version to validate exact details)
- 2 vCPU with 2200 Mhz
- 2GB RAM
- 80 GB disk

#### Collocated Server

- Label: All Servers except Web Server
- Details: (12.5 v1.0 OVA used, check current OVA for your version to validate exact details)
- 4 vCPU with 4000 Mhz
- 20 GB RAM (20 GB reservation)
- Disks:
- 80 GB disk – OS and SQL Executables
- 50 GB disk – ECE Application
- 300 GB disk – Databases

### Install Windows Server on All 4 Servers

(As of 12.5, Windows 2016 must be used, check the current documentation prior to install)

### Format the 50 GB and 300 GB Disks on the Two Collocated Servers

### Install SQL Server on the Two Collocated Servers

(As of 12.5, SQL Server 2016 Enterprise Edition must be used, check the current documentation)

prior to install)

The same SQL Server Instance name must be used on both servers. There is no requirement that a specific instance name be used or that the default instance be used. The example in this document uses the default instance.

**Caution:** It is critical that SQL Server Enterprise Edition be used. ECE requires all three databases to be in the same SQL Server instance or Availability Group. While SQL Server Standard does support AlwaysOn Availability Groups, it only supports a single database in each. If the incorrect version of SQL Server is installed, installation of ECE may appear to succeed, but you will be unable to join all three databases to the Availability Group. Prior to installation of ECE, if you find that the edition of SQL Server installed is incorrect, you can use the SQL Server installation ISO and select the option to upgrade a current installation of SQL Server .

## Preinstallation Steps


### Step 1. Add Required Windows Features

Before you start any configuration, you need to add two Roles & Features to both collocated servers.


Repeat these steps on both collocated servers.

1. From the **Server Manager**, select **Manage**, then **Add Roles and Features**.
2. Select **Next** until you reach the **Server Roles** page.
3. Scroll down to **File and Storage Services**, then select to expand. Select **File and iSCSI Services**, then select to expand.
4. In the list, find and place a check-box beside both **DFS Namespaces** and **DFS Replication** as shown in the image.






5. You may receive a pop-up box that states additional tools are required, select the **Add Features** button to accept this.




6. Select **Next** to go on to the **Features** page.

7. Find the **Failover Clustering** in this list and place a check-box beside of it.



8. If you receive a pop-up that states additional tools are required, select the **Add Features** button to accept this.



9. Select **Next**, then check the box beside **Restart the destination server automatically if required**, and select **Finish**.
10. Monitor install until it is complete. Allow server to restart if necessary.

## Step 2. Prepare Active Directory

Before you start the configuration of the Windows Server Failover Cluster and SQL Availability Group Cluster, there are several configuration items that need to be performed in Active Directory with an account that has Domain Admin rights.

**Warning:** It is critical that these steps are followed very carefully as failure to do these results in the in failure two clusters to work.

1. **Create required Service Accounts** You need to create two User Accounts in Active Directory to be used as Service Accounts. These accounts only need to be a member of **Domain Users** group, but must be configured so that their password either does not expire or has a very long expiration time. If you need to change the password for these accounts

once the system is in operation, you require a full outage of ECE.

This document does not cover or show the specific steps to create these as it is a matter of preference for where the accounts physically reside in the Active Directory tree, the object names, and other configuration items.

As a reminder, these two accounts are used throughout the rest of this document.

SQL Server Service Account – SqlServerSvc

ECE Service Account – ECESvc

2. **Prestage the Cluster Name Object (CNO)** You need to create a CNO in Active Directory for use by the WSFC. When all of the preinstallation steps have been completed, Active Directory contains two CNOs.

- The first CNO is the name of the WSFC. You create this manually in the steps that follow. This name is needed to perform the initial setup of WSFC and then later, to connect the WSFC management console to the cluster.

- The second CNO is the name of the SQL Server AG Cluster. This is automatically created by the Availability Group Wizard. ECE uses this name for all database communications. In addition, you use this name when you use SQL Server Management Studio to perform most database related tasks. Of the two names, the second is the most important and is used in day-to-day operations and troubleshooting.

**Note:** Both of these names are limited to 15 characters as they are NetBIOS names. As a reminder, this document uses these CNOs:


CC2K125ECEFOC – CNO for the WSFC Failover Cluster

CC2K125ECEDB – CNO for the SQL Server Availability Group cluster

In Active Directory Users and Computers, expand the domain, then create a new Organizational Unit to hold the CNOs. Create the WSFC CNO as follows. In the new OU, right-click and select **New**, then select **Computer**. Type the name for the computer object, then select **OK**. As a best practice, right-click the computer object that you just created and select **Properties**. Select the **Object** tab, check the box marked, **Protect object from accidental deletion**, then select **OK**. Finally, right-click the computer object and select **Disable Account**. Select **Yes** to confirm.

**Note:** The computer account must be disabled so that the cluster creation process can confirm that it is not currently in use by a computer or cluster.

3. **Grant User Permissions** You need to grant permissions to control the CNO to the user account that you use when you run the WSFC wizard. In **Active Directory Users and Computers**, select the **View** menu, then ensure that **Advanced Features** has a check beside it. If this is not selected, select it, then expand the Active Directory tree again.



Assign permissions to the CNO as follows. Right-click the CNO, then select **Properties**. Select the **Security** tab, then select **Add**. Type in the name of the user account, or a group of which the user is a member, then select **OK**. Select the user or group that you just added, then in the bottom section, select the **Allow** check-box next to **Full Control**. Select **OK**.

4. **Grant CNO Permissions** In order for failover to work properly, the CNO must be able to control the computer objects in the OU. This allows the WSFC CNO to create the SQL Server CNO through the wizard. In **Active Directory Users and Computers**, select the **View** menu, then ensure that **Advanced Features** has a check beside it. If this is not selected, selected it and then expand the Active Directory tree again. Right-click the OU that you created and select **Properties**. Select the **Security** tab, then select the **Advanced** button. In the **Advanced Security Settings** dialog box, select **Add**. Select **Select a principal**. In the **Select User, Computer, Service Account or Group** box, select the **Object Types...** button. Check the box beside **Computers**, then select **OK**. Type in the CNO name, then select **OK**. You see a warning that you are about to add a disabled object, select **OK** as this is expected. Ensure that the **Type** is **Allow** and that the **Applies to:** is set for, **This object and all descendant objects**. In the **Permissions** list, find **Create Computer objects** and **Delete Computer objects**, and check the box beside of each. Select **OK**.
5. **Register SPN** Because ECE HA install requires the use of Windows Authentication to access the SQL Server, it is mandatory to register the SPN in Active Directory. This step does not require the SQL Server AG to be configured. Only the SQL Server Agent account must be configured. **Note:** You must be a member of Domain Admins in order to perform these tasks. Before you begin, please have this information available.

From any server which is currently on the domain, and while logged in as a member of the Domain Admins group, open a **Command Prompt** as Administrator. Run these commands. Update each them to match your environment.

In the setspn command, the :MSSQLSERVER is the SQL Instance name you chose. If you

```
setspn -A MSSQLSvc/CC2K125ECEDB.massivedynamic.com:1433 MASSIVE\SqlServerSvc
```

```
setspn -A MSSQLSvc/CC2K125ECEDB.massivedynamic.com:MSSQLSERVER MASSIVE\SqlServerSvc
setspn -A MSSQLSvc/CC2K125ECEDB:1433 MASSIVE\SqlServerSvc
setspn -A MSSQLSvc/CC2K125ECEDB:MSSQLSERVER MASSIVE\SqlServerSvc
```

Run this command to ensure that the SPN registration was successful.

```
setspn -Q MSSQLSvc/CC2K125ECEDB*
```

You should see output similar to this.

```
Checking domain DC=massivedynamic,DC=com
CN=SQL Server Service,OU=Service Accounts,OU=Special Accounts,DC=massivedynamic,DC=com
MSSQLSvc/CC2K125ECEDB:MSSQLSERVER
MSSQLSvc/CC2K125ECEDB:1433
MSSQLSvc/CC2K125ECEDB.massivedynamic.com:MSSQLSERVER
MSSQLSvc/CC2K125ECEDB.massivedynamic.com:1433
MSSQLSvc/CC2K125ECEAB:MSSQLSERVER
MSSQLSvc/CC2K125ECEAB:1433
MSSQLSvc/CC2K125ECEAB.massivedynamic.com:MSSQLSERVER
MSSQLSvc/CC2K125ECEAA.massivedynamic.com:1433
MSSQLSvc/CC2K125ECEAA:MSSQLSERVER
MSSQLSvc/CC2K125ECEAA:1433
MSSQLSvc/CC2K125ECEAA.massivedynamic.com:MSSQLSERVER
```

```
Existing SPN found!
```

Validate configuration of SQL Service Account. Open **Active Directory Users and Computers** from either a domain controller or a machine with the Active Directory Management Tools installed. Navigate to the SQL Service Account in the tree, right-click the account and select **Properties**. Select the **Account** tab, then in the **Account options:** box, scroll through and ensure that these options NOT are selected. **Account is sensitive and cannot be delegated** Do not require Kerberos preauthentication Select the **Delegation** tab and ensure that the **Trust this user for delegation to any service (Kerberos only)** IS selected.

**Note:** If you do not see the Delegation tab, then either the setspn -A commands have not been run or the Domain Controller you are on does not contain an up-to-date copy of the configuration. Either connect to a Global Catalog Domain Controller, wait until domain replication completes, or return to steps 5.2 and 5.3 to validate that the setspn -A commands were run correctly. Validate configuration of Servers In **Active Directory Users and Computers**, navigate to the computer account for each collocated server. Right-click and select **Properties**, then select the **Delegation** tab. Ensure that the **Trust this computer for delegation to any service (Kerberos only)** is selected. After you make any required changes, select **OK**.

### Step 3. Create Required Directories

Unlike the standalone installation of ECE, you need to create a directory to use for the File server role. This directory, known as the File Server Directory or Shared directory, is used in the DFS Namespace and Replication group. This directory MUST be separate from the ECE Home Directory.

As a reminder, in this document, ECE is installed on the E: drive.

These directories are created in this section.

Shared directory – E:\ECEFile



SSIS directory – E:\ssis\_data  
SQL backup directory – F:\MSSQL\Backups  
SQL data directory – F:\MSSQL\Data

Perform these steps on both collocated servers.

1. **Create the shared directory** On the E drive, create a new directory named ECEFile. Right-click the directory and select **Properties**, then select the **Sharing** tab. Select the **Advanced Sharing...** button. Check the **Share this folder** box, then select the **Permissions** button. In the **Permissions for ECEFile** box, select the **Add...** button. In the **Select Users, Computers, Service Accounts, or Groups** box, enter the name of the service account you created to run the ECE service, select **Check Names**, then select **OK**. Ensure that the account you just added is selected in the list, then check the box in the **Allow** column beside **Full Control**. Select **OK** to return to the Advanced Sharing properties box. Select **OK**, then **OK** again.
2. **Create the SSIS directory** On the E drive, create a new directory named ssis\_data. Right-click the directory and select **Properties**, then select the **Security** tab. Select the **Edit** button, then in the **Permissions for ssis\_data** box that pops-up, select the **Add...** button. In the **Select Users, Computers, Service Accounts, or Groups** box, type the name of the service account you created to run the SQL Server service, select **Check Names**, then select **OK**. Note, if you did not create an account to run the SQL Server, then type the name of the service account created for the ECE Service. Check the box in the **Allow** column beside **Modify**. This automatically grants **Write** permission, but scroll down to ensure that there is not a check-box in the **Deny** column for any of the permissions fields. Select **OK**, then **OK** again.
3. **Create the SQL Server data and backup directories** On the F: drive, create a new folder named MSSQL. Inside of the MSSQL folder, create two other folders, Backup and Data.

## Step 4. Configure Distributed File System


As described in the terminology section, DFS must be configured as a Domain Namespace and must also have a Replication Group to synchronize the two servers. The DFS feature was added to each collocated server in the previous steps. Next, configure both the Namespace and Replication Group.

Unlike most previous steps, you only need to complete this on one of the two servers. Once setup, either server can manage DFS by use of the management snap-in.

**Tip:** It is generally easier to troubleshoot if you use the side-A server for all setup tasks.

1. **Create the Namespace** From the **Server Manager**, select **Tools** then **DFS Management**. In the **DFS Management** snap-in, select the **Namespaces** node, then in the **Actions** pane at the right, choose **New Namespace**. Type the name of the side-A, collocated ECE server in the **Server** name box in the **New Namespace Wizard** box, then select **Next >**.





On the **Namespace Name and Settings** page, type the Namespace root name in the **Name** field of the next screen. In this document, the Namespace name is, **ECE\_Root**. Select the **Edit Settings...** button. In the **Edit Settings** pane, select the **Administrators have full access; other users have read-only permissions** option, then select **OK**. Select **Next >** to continue to the next page.

Edit Settings

Namespace server:  
CC2K125ECEAA

Shared folder:  
ECE\_Root


Local path of shared folder:  
C:\DFSRoots\ECE\_Root Browse...

Shared folder permissions:


- All users have read-only permissions
- All users have read and write permissions
- Administrators have full access; other users have read-only permissions
- Administrators have full access; other users have read and write permissions
- Use custom permissions: Customize...

OK Cancel

On the **Namespace Type** page, ensure that the **Domain-based namespace** option is selected. Leave the **Enable Windows Server 2008 mode** option checked, then select **Next >** to continue to the next page.




On the **Review Settings and Create Namespace** page, note the **Namespace Name**, this is the UNC path where you access the share. There is also a local path listed similar to, **C:\DFSRoots\**, the local path of namespace shared folder is NOT the same as the physical location where the DFS files are located. After the namespace is created, The local path contains a pointer folder to the shared folder location. The files are physically stored in the shared folder location.



Check the **Confirmation** page to ensure that the Task shows Success and that there were no Errors. Select **Close** to return to the **DFS Management** pane.

2. **Add the Namespace Server** In the **DFS Management** snap-in, expand, **DFS Management > Namespaces**, then select the Namespace that you created. In the **Actions** pane at the right, choose **Add Namespace Server....** In the **Add Namespace Server** box, type the name of the side-B collocated server in the **Namespace server:** box. Select the **Edit Settings** button, then select the **Administrators have full access; other users have read-only permissions** option, then select **OK** to add the side-B server. Select the **Namespace Servers** tab and check that both servers are listed.
3. **Add Folder and Folder Targets and Configure Replication** In the **DFS Management** snap-in, expand, **DFS Management > Namespaces**, then select the Namespace that you created. In the **Actions** pane at the right, choose **New Folder...** In the **New Folder** box, type a name for the share in the **Name:** box. When you install ECE, this is the folder name in the DFS Root. In this document, the folder name is, **ECE**. Select the **Add...** button under the **Folder targets** box. In the **Path to folder target:** box, type the UNC path to the side-A server and share created in step 3. In this document, this is **\\CC2K125ECEAA\ECEFile**.



Select **OK** to add the first target. Select the **Add...** button once again and add the side-B server and share created. In this document, this is **\\CC2K125ECEAB\ECEFile**. Select **OK** to add the second target. Back in the **New Folder** box, and after you add the Folder target to each ECE server, select **OK** to complete the **New Folder** dialog.

New Folder

Name:  
ECE


Preview of namespace:  
\\massivedynamic.com\ECE\_Root\ECE

Folder targets:  
\\CC2K125ECEAA\ECEFile  
\\CC2K125ECEAB\ECEFile

Add... Edit... Remove


OK Cancel

When prompted to setup **Replication**, select **Yes**. In the **Replicate Folder Wizard**, select **Next >** through the first two screens. At the **Primary Member** page, select either server. If there are already files in the two directories which have the same name, whichever server is chosen as primary is considered authoritative. For an initial install, this is not an issue as there must not be any files or folders in the ECE File share. After you choose the primary server, select **Next >**. In the **Topology Selection** pane, ensure that the **Full mesh** option is chosen, then select **Next >**. In the **Replication Group Schedule and Bandwidth** pane, select the **Replicate continuously using the specified bandwidth** option and leave the **Bandwidth** selection as **Full**. Select **Next >**. Review the final page, then choose the **Create** button.



On the **Confirmation** page, ensure that all **Tasks** show Success and that there are no **Errors** shown.





Select **Close** to return to the **DFS Management** pane. You may see an information box with the title, **Replication Delay**. Select **OK** to close this as this simply warns you that replication is not available until all servers in the group have the configuration. For the the initial setup in most environments, this should be very fast. In larger Active Directory domains, there may be a delay before this is complete.

4. **Configure Staging folder Quota** This topic to be updated at a later time.

5. **Test the DFS Namespace and Replication Group** Open the **Windows File Explorer** on the side-A collocated server. Navigate to the Shared Directory. In this document, this is E:\ECEFile. Open **Notepad** and create a new text file with the content, 'Side A Creation'. **Save** this as E:\ECEFile\RepITest.txt, then close **Notepad**. Switch to the side-B collocated server and open **Windows File Explorer**. Navigate to the Shared Directory and confirm that you see the RepITest.txt file. If you do not see this immediately, wait a minute or two for Replication to synchronize. Open the file on side B and add a new line with the content, 'Side B Update', then **Save** the file. Switch back to the side-A server and open the file once more to confirm that you now see both lines. While still on the side-A collocated server, type the full UNC path to the DFS share into the location bar in **Windows File Explorer**. Example: \\massivedynamic.com\ECE\_Root\ECE. Verify that you see the RepITest.txt folder. Create a new folder named, **DFSTest**. Move the RepITest.txt file into this folder. In **Windows File Explorer** navigate to the local Shared Directory and validate that you see the DFSTest directory and that the RepITest.txt file has been moved correctly. Finally, switch back to the side-B server and validate that the new directory is present and the file has been moved.



## Step 5. Configure Windows Server Failover Cluster

These steps need to be done from only one server.

**Warning:** It is imperative that you complete the steps in **Prepare Active Directory** before you start this section. Failure to do so may result in a cluster which is either not setup or is only partially setup.

1. **Initial Cluster Setup** From **Server Manager**, select **Tools** then **Failover Cluster Manager**. In the **Failover Cluster Manager** snap-in, choose **Create Cluster...** in the **Actions** pane on the right. Select **Next >** on the **Before You Begin** page, then in the **Select Servers** page, add both of the collocated servers. Ensure that the validation check succeeds and that you see both servers listed by fully qualified name in the **Selected servers:** box, then select **Next >** to continue to the next page.

Create Cluster Wizard

### Select Servers

Before You Begin

Select Servers

Validation Warning

Access Point for Administering the Cluster

Confirmation

Creating New Cluster

Summary

Add the names of all the servers that you want to have in the cluster. You must add at least one server.

Enter server name:  Browse...


Selected servers:

- CC2K125ECEAA.massivedynamic.com
- CC2K125ECEAB.massivedynamic.com


Add Remove

< Previous Next > Cancel


On the **Validation Warning** page, leave the option selected as **Yes. When I click Next, run configuration validation tests, and then return to the process of creating the cluster**, then select **Next >**.




On the **Validate a Configuration Wizard**, select **Next >**.



Select **Next >** through the Wizard and allow the tests to proceed. You can see the example validation in the image.



After all tests complete, select **View Report...** to show the report in a browser. You should not have any failures. The Network category may show the status of Warning with the message that the nodes are only accessible by one network interface. You can safely ignore these. If you see any warnings about software update levels, ensure that you apply the same patches to both servers. You can see an example summary screen with the Network warning and a System Configuration warning in the image. The System Configuration warning in this example is because one server did not have a Windows Defender Update which the other did. Select **Finish** after you review the report.



Select **Next >** to reach the **Access Point for Administering the Cluster** pane. Use this information to complete this page, then select **Next >** once complete. **Cluster Name** – This must be the CNO configured for the Failover Cluster. This must NOT be the name that you defined for use by ECE to access the database. **Address** field of Networks box – This is the IP address that your cluster uses. If your collocated servers are in two different subnets, you need an IP address in each subnet. When the cluster switches the owner node, then the WSFC updates DDNS to reflect the correct IP. This ensures that the name is always accessible.

**Note:** You are only be able to change the host portion of the Address field.

Create Cluster Wizard

## Access Point for Administering the Cluster

Before You Begin

Select Servers

**Access Point for Administering the Cluster**

Confirmation

Creating New Cluster

Summary

Type the name you want to use when administering the cluster.

Cluster Name:

**i** The NetBIOS name is limited to 15 characters. One or more IPv4 addresses could not be configured automatically. For each network to be used, make sure the network is selected, and then type an address.

|                                     | Networks       | Address       |
|-------------------------------------|----------------|---------------|
| <input checked="" type="checkbox"/> | 14.10.162.0/24 | 14.10.162.170 |
| <input checked="" type="checkbox"/> | 14.10.172.0/24 | 14.10.172.170 |

< Previous    Next >    Cancel

On the **Confirmation** page. Ensure that **Add all eligible storage to the cluster** is checked, then select **Next >**.

**Note:** The cluster is created immediately after you select **Next >**. Review the output to ensure there are no errors, select **Finish** on the **Summary** screen.

**Note:** You may see a message that there was no appropriate disk found as the witness disk. This is corrected in the next steps.

Create Cluster Wizard

## Summary

Before You Begin

Select Servers

Access Point for Administering the Cluster

Confirmation

Creating New Cluster

**Summary**

**w** You have successfully completed the Create Cluster Wizard.

|               |   |
|---------------|---|
| Node Majority |   |
| IP Address    |   |
|               | 14.10.162.170   |
|               | 14.10.172.170   |
| Warnings      |   |
|               | * No appropriate disk could be found for the witness disk.  |
|               | * An appropriate disk was not found for configuring a disk witness. The cluster is not configured with a witness. As a best practice, configure a witness to help achieve the highest availability of the cluster. If this cluster does not have shared storage, configure a File Share Witness or a Cloud Witness. |

To view the report created by the wizard, click View Report.  
To close this wizard, click Finish.

View Report...

Finish

2. **Configure Cluster Quorum** Since ECE does not have an extra physical drive that is shared between the two nodes, Windows Server Failover Cluster requires a shared UNC path drive to act as the quorum drive. The quorum does not require much space, 500 megabytes is ideal. It must be a drive though that is available to both collocated servers, has some level of redundancy/high-availability, but is not part of the local DFS share. For a lab system, there are several ways to implement this. For a production system though, the placement of this drive is quite important. It is outside the scope of this document to cover how to setup the shared quorum drive.

Once you allocate the share in your environment, setup the Quorum drive location . In the **Failover Cluster Manager**, select the new cluster that you created, then select **More Actions > Configure Cluster Quorum Settings...** in the **Actions** pane on the right. In the **Configure Cluster Quorum Wizard** box, select **Next >** past the first page. On the **Select Quorum Configuration** page, choose the **Select the quorum witness** option, then select **Next >**. On the **Select Quorum Witness** page, choose **Configure a file share witness** option, then select **Next >**. On the **Configure File Share Witness** page, in the **File Share Path:** box, type the UNC path to the file share or choose **Browse** to select a network location. Select **Next >** when this is done. Review the next page, then select **Next >**. Finally, review the **Summary** page, and select **Finish**.

3. **Review Cluster** At this point, the cluster should be fully setup and confirmed to work properly. Review the Failover Cluster Manager for any errors. In the **Cluster Events** node, you can find Windows Events which are directly related to the WSFC cluster. There are two which you can safely ignore in a dual-subnet WSFC. These are Event ID 1069 and 1045. Because the IP address that matches the subnet of the non-primary server is not be accessible until the cluster switches sides, it is expected that these show up. If you see other errors, investigate and resolve each.

Another helpful tool is the **Validate Cluster** tool. This is what was run in step 5.1.5. If you run it after you set up the cluster, you can check for any errors or warning.

**Note:** The management and support of the WSFC is outside the scope of this document. Please contact a Microsoft professional for support if needed. **Warning:** It is extremely important that the WSFC cluster is setup and works without error before you proceed to setup the SQL AG or install ECE. It is much more difficult to troubleshoot and fix the WSFC cluster after the SQL AG or ECE has been installed.

## Step 6. Configure SQL Server

The last step to prepare for the installation is to create the SQL Server Availability group. Remember, you must run SQL Server 2016 Enterprise Edition to support ECE. These steps do all work with SQL Standard Edition. You are even be able to install ECE and associate one database with the Availability Group. When you attempt to associate more than one database though, SQL Server returns an error. If you receive this, you must first do an in-place upgrade of SQL Server from Standard to Enterprise, then you can add the databases to the Availability Group.

Before you begin, document this information and have it available.


| Item               | Example      | Value |
|--------------------|--------------|-------|
| CNO for SQL Server | CC2K125ECEDB |       |

|                                |               |
|--------------------------------|---------------|
| Listener                       |               |
| IP Address in Subnet on side A | 14.10.162.171 |
| IP Address in Subnet on side B | 14.10.172.171 |
| SQL Listener Port              | 1433          |

**Note:** Values used in this document are shown in the Example column.

1. **Enable SQL Server Availability Groups** Do the next steps on both SQL Servers. From the Start Menu, open the folder, Microsoft SQL Server 2016, then select **SQL Server 2016 Configuration Manager**. In the **Sql Server Configuration Manager**, choose **SQL Server Services**, then right-click **SQL Server (MSSQLSERVER)** and choose **Properties**. Note, if you used an instance name other than the default when you installed SQL Server, the service name contains your instance name in the parentheses. In the **SQL Server (MSSQLSERVER) Properties** page, choose the **AlwaysOn High Availability** tab. Validate that you see the Windows failover cluster name that was created. If you do not, go back and troubleshoot your WSFC setup. If you do, check the **Enable AlwaysOn Availability Groups** box.





Select **OK** to apply this change. You may see a message that the changes do not take effect until the service is stopped and restarted, select **OK**. Right-click and restart the **SQL Server (MSSQLSERVER)** service.

2. **Create a Temporary Database** Before you start the setup of the Availability Group, you need to create a temporary database to be used in the Wizard. This is not the same as the SQL Server's TempDB, it is a user database but can be removed after ECE is setup. The database simply needs to exist and can be quite small with no data in it. Two different ways are shown to create this database.

Open **SQL Server Management Studio** and connect to one of the two collocated servers.

**Tip:** It is generally easier to troubleshoot if you use the side-A server for all SQL AG setup tasks. This also helps to ensure that the side-A server is the Primary Replica when the setup



is complete. Use one of these the database Via GUI Right-click **Databases** and choose **New Database**. Give the database a unique name, accept the default **Initial Size (MB)** values that SQL Server uses. Select the **Options** node and ensure that **Recovery model:** is set to **Full**. Select **OK**. Via T-SQL

This creates a database named AGTemp with a data and log file of 1MB.

Select **New Query**. Paste the TSQL that follows. Ensure that you make any required changes to place the data files where you want.

```
CREATE DATABASE [AGTemp]
ON PRIMARY
(NAME = N'AGTemp' , FILENAME = N'F:\MSSQL\DATA\AGTemp.mdf' , SIZE = 1024KB, FILEGROWTH =
8KB )
LOG ON
(NAME = N'AGTemp_log' , FILENAME = N'F:\MSSQL\DATA\AGTemp_log.ldf' , SIZE = 1024KB ,
FILEGROWTH = 8KB )
GO
```

```
ALTER DATABASE [AGTemp] SET RECOVERY FULL
GO
```

Select **Execute** to run this. **Make a Full Database Backup After You Create the Database** You can use either the GUI method or the TSQL method to create this backup. Both methods are shown next, and assume that you already have **SQL Server Management Studio** open and that you use the AGTemp database name. Via GUI Right-click the **AGTemp** database and choose **Tasks > Back Up...** Check the **Back Up Database - AGTemp** box that comes up and ensure that the **Backup type:** is set to **Full** and that the **Destination** is **Disk**. Also ensure that the location shown is correct for your system. Use the **Add / Remove** buttons to make any necessary changes. Select **OK** and ensure that you see **The backup of database 'AGTemp' completed successfully**. Via T-SQL Select **New Query**. Paste the TSQL that follows. Ensure that you make any changes required for both database name and backup file location.

```
BACKUP DATABASE [AGTemp]
TO DISK = N'F:\MSSQL\Backups\AGTemp.bak'
WITH NAME = N'AGTemp-Initial Full Backup',
COMPRESSION, STATS = 25
GO
```

Select **Execute** to run this. Check the **Messages** tab to see a line similar to this.


BACKUP DATABASE successfully processed 322 pages in 0.054 seconds (46.567 MB/sec).

3. **Create the Availability Group** Before you start, all previous steps must be done. You must have this information on hand.


SQL Server Availability Group CNO

IP Address(es) for CNO


1. In **SQL Server Management Studio**, right-click the **Always On High Availability** node and choose, **New Availability Group Wizard**.
2. Select **Next >** past the Introduction page.
3. Fill out the **Specify Availability Group Options** page as follows. Type a display name for the Availability Group into the **Availability group name** box. While this name does not need to be the same as the CNO, it is generally best to use this as it simplifies management. The examples shown in this document use the same name for both. The only valid **Cluster type** is **Windows Server Failover Cluster**. Ensure that **Database Level Health Detection** is not selected. Optionally, select **Per Database DTC Support**. Select **Next >** to proceed.



4. On the **Select Databases** page, check the box beside of the temporary database created for this purpose. Ensure that the **Status** shows **Meets Prerequisites**. If it does not, fix any issues reported.



5. Fill out each tab on the **Specify Replicas** page as follows. On the **Replicas** tab. Select **Add Replica...** below the **Availability Replicas:** box. In the **Connect to Server** box, type the host name of the other collocated server, then select **Connect**. Change the **Availability Mode** for each **Server Instance** to **Synchronous commit**. Change the **Readable Secondary** for each **Server Instance** to **Yes**.



On the **Endpoints** tab. Ensure that the port numbers are open and that the firewall rules have been updated to allow these to pass. Make any desired changes to the ports. On the **Backup Preferences** tab. Choose the option, **Any Replica**. On the **Listener** tab. Choose the **Create an availability group listener** option, then fill out these details. **Listener DNS Name:** Provide the NetBIOS host name of the **SQL Server Availability Group CNO**. **Port:** Provide the SQL Listener port you have chosen. This is generally **1433**, but can be changed to meet your specific needs. If you change this port, ensure that you open the firewall on both servers and that you enter the port in the databases section of the ECE install later in the document. **Network Mode:** Select **Static IP**. Select the **Add...** button below the **Subnet** and **IP Address** box. In the **Add IP Address** box, choose the appropriate **Subnet:** from the drop-down. In the **IPv4 Address** box, type the full **IPv4** address you have allocated for the SQL Server Availability Group. Repeat as required for each **Subnet** in your cluster.

**Specify Replicas**

Introduction  
Specify Options  
Select Databases  
**Specify Replicas**  
Select Data Synchronization  
Validation  
Summary  
Results

Specify an instance of SQL Server to host a secondary replica.

Replicas Endpoints Backup Preferences **Listener** Read-Only Routing

Specify your preference for an availability group listener that will provide a client connection point:

Do not create an availability group listener now  
You can create the listener later using the Add Availability Group Listener dialog.

**Create an availability group listener**  
Specify your listener preferences for this availability group.

Listener DNS Name: CC2K125ECEDB

Port: 1433

Network Mode: Static IP


| Subnet         | IP Address    |
|----------------|---------------|
| 14.10.162.0/24 | 14.10.162.171 |
| 14.10.172.0/24 | 14.10.172.171 |

Add... Remove

< Previous Next > Cancel


You can skip the **Read-Only Routing** tab as ECE currently does not use this feature. Select **Next >** after you complete the tabs.

6. Fill out the **Select Initial Data Synchronization** page as follows. Choose the **Full database and log backup** option. In the **Specify the file share path in Windows format:** box, type, or browse to a file share which both servers can access. You can create a directory on the E: drive of one of the servers, share this, then use it for the initial setup. After you complete this page, select **Next >**.



7. On the **Validation** page, review checks. Ensure that all return as Success. If there are any that fail, review the reason and take corrective action. If any changes are required, use the **< Previous** and **Next >** buttons to step through the screens and make any required changes. Select the **Re-run Validation** after you correct any issues to validate. When all validation checks succeed, select **Next >**.









New Availability Group

 **Validation**

Introduction  
Specify Options  
Select Databases  
Specify Replicas  
Select Data Synchronization  
**Validation**  
Summary  
Results

Help

**Results of availability group validation.**


| Name  | Result                  |
|---|-------------------------|
|  Checking for free disk space on the server instance that hosts secondary replica CC2K125...   | <a href="#">Success</a> |
|  Checking if the selected databases already exist on the server instance that hosts second...  | <a href="#">Success</a> |
|  Checking for the existence of the database files on the server instance that hosts seconda... | <a href="#">Success</a> |
|  Checking for compatibility of the database file locations on the server instance that host... | <a href="#">Success</a> |
|  Checking whether the endpoint is encrypted using a compatible algorithm                       | <a href="#">Success</a> |
|  Checking shared network location  | <a href="#">Success</a> |
|  Checking replica availability mode  | <a href="#">Success</a> |
|  Checking the listener configuration   | <a href="#">Success</a> |

Re-run Validation

< Previous   Next >   Cancel


8. Review the **Summary** page for accuracy, then select **Finish.** to create the Availability Group.





9. Select the **More details** drop-down button to watch each task. If you encounter an error, manually correct the issue or clean up the Availability Group completely from both servers (and Active Directory if necessary), then repeat the configuration.





4. **Verify Availability Group Setup** Once the wizard has run successfully, do this to validate that the Availability Group is setup and works properly. Note, it can take several minutes for the Availability Group setup to be complete. After you see the **Success** screen, the servers still must copy over the database backup, then restore it on the secondary, then setup the High Availability and Disaster Recovery (HADR) connection. Unless the two ECE collocated servers are on the same physical LAN, you may need to wait 5-10 minutes before you do these checks.

Verify that the Availability Group exists on the primary replica.

Note, the primary replica is generally be whichever side you ran the wizard from initially. The side which is primary is not important at this time, but you do need to know this for the post-install configuration steps.


While still in **SQL Server Management Studio** on the side you ran the Wizard from, right-click the server name in the **Object Explorer** pane on the left and choose **Refresh**. Expand **Databases** and check that the temporary database you created now shows **(Synchronized)**. Expand **Always On High Availability > Availability Groups** then finally expand the Availability Group name you created and validate each of these. Ensure that you see **(Primary)** beside the AG Name. Expand each node under the AG name and validate each of these. In **Availability Replicas**, check that both servers listed. One is marked as **(Primary)** the other is marked as **(Secondary)**. In **Availability Databases**, check that the temporary database used to run the wizard is shown. It should have a green indication next

to the cylinder icon. In **Availability Group Listeners**, check that the listener name created in the wizard exists. Right-click the **listener** and choose **Properties**. Check that the port and IP addresses are all as configured. Verify that the Availability Group exists on the secondary replica. Open **SQL Server Management Studio** on the second collocated server and connect to the server by name. Expand **Databases**, and check these items. Ensure that you see the database you created on side A to run the wizard. The wizard should have automatically created this database on side B. Beside the database name, you should see **(Synchronized)**. If you do not, see the steps in the Availability Group checks section. Expand down to **Always On High Availability > Availability Groups** then finally expand the Availability Group name you created and validate these items. Ensure that you see **(Secondary)** beside the AG Name. Expand each node under the AG name and validate these items. In **Availability Replicas**, check that both servers are listed. When you view this from the secondary node, the primary node is listed, but have no indication beside of it. The node you are on shows **(Secondary)**. In **Availability Databases**, check that the temporary database used to run the wizard is shown. It should have a green indication next to the cylinder icon. If it does not, do these steps. Right-click the database and choose **Join Database**. Select **OK** in the **Join Database to Availability Group** box and check that there are no errors. Refresh the **Databases** node and validate that the database now shows **(Synchronized)**. In **Availability Group Listeners**, check that the listener name created in the wizard exists. Right-click the listener name and choose **Properties**. Check that the port and IP addresses are all as configured. Verify that the Availability Group is accessible via the Listener. Either open a new **SQL Server Management Studio** or in an already open **SQL Server Management Studio** select **Connect > Database Engine...** from the Object Explorer on the left. In the **Connect to Server** box, type the name of the listener that you created, then choose **Connect**. You should now see the same nodes as are present on the primary replica. Expand **Databases** and verify that you see the temporary database and that it shows **(Synchronized)**. Expand the other nodes as desired. Verify via the Availability Group Dashboard


SQL Server has built in a dashboard which can be used to monitor the Availability Group health, events, and perform certain functions like Failover. This is an extremely useful tool to understand.

Via **SQL Server Management Studio**, connect to either the Listener name or the primary replica. In a production system where you do not know which node is primary, connect with the Listener name. Right-click **Always On High Availability** and choose, **Show Dashboard**. Alternatively, expand **Always On High Availability > Availability Groups** and right-click the Availability Group name and choose **Show Dashboard**. If you chose **Show Dashboard** from the **Always On High Availability** node or from the **Availability Groups** node, you see a dashboard that shows the Availability Group name, the current primary replica, failover mode, and whether there are any current issues. While ECE does not require the use multiple Availability Groups on the same set of servers, a system with more than one Availability Group shows all Groups on this page and the current, high-level details.

From here, select the hyperlink name of the Availability Group.



If you chose **Show Dashboard** from the Availability Group name, or if you selected on the hyperlink from the summary dashboard, you now see a dashboard with far more details. The key items to look for here are as follows. If you see errors, select the links **Availability group state**: This should be **Healthy**. **Availability replica**: This should list both servers in the AG and indicate the role of each. In the bottom portion of the dashboard, you see both servers listed with all databases that are a member of the AG. Both servers should list the same number of databases, **Synchronization State** should show **Synchronized**, and **Failover Readiness** should show **No Data Loss**.



5. **Update Dynamic DNS (DDNS) Configuration** As a best practice, the DDNS configuration must be updated. By default, DDNS records are refreshed every 20 minutes. Microsoft recommends that this value be changed to 300 seconds. This must be done on both collocated servers. **Note:** The commands in this section must be entered in sequence, while in the same PowerShell window. If the window is closed accidentally, you must start with the first command again to ensure that the subsequent commands do not fail. There is no issue if the same command is executed twice, but you must not skip any steps. Open **PowerShell** window via **Run as Administrator**. Type, or copy and paste the command to import the FailoverClusters module.

Import-Module FailoverClusters

Identify the resource name. Type, or copy and paste the commands into the PowerShell

window. Change the input value of **\$nameAGCluster** parameter to match the Availability Group Name you chose.

```
$nameAGCluster = "CC2K125ECEDB"  
Get-Cluster | Get-ClusterResource | ?{$_ .ResourceType -like "Network Name" -and  
$_ .OwnerGroup -eq $nameAGCluster}
```

In the output, identify the value of **Name**.

```
PS C:\Windows\system32> Get-Cluster | Get-ClusterResource | ?{$_ .ResourceType -like  
"Network Name" -and $_ .OwnerGroup -eq "CC2K125ECEDB"}
```

```
Name State OwnerGroup ResourceType  
-----  
-----
```

```
CC2K125ECEDB_CC2K125ECEDB Online CC2K125ECEDB Network Name
```

Update mandatory settings Type, or copy and paste the commands into the PowerShell window. Change the input value of **\$nameResource** to match your environment.

```
$nameResource = "CC2K125ECEDB_CC2K125ECEDB"  
Get-ClusterResource $nameResource | Set-ClusterParameter HostRecordTTL 300
```

Ensure that the properties were stored. The warning message is expected.

```
PS C:\Windows\system32> Get-ClusterResource $nameResource | Set-ClusterParameter  
HostRecordTTL 300
```

```
WARNING: The properties were stored, but not all changes will take effect until  
CC2K125ECEDB_CC2K125ECEDB is taken offline and then online again.
```

Repeat on the commands second collocated server. Restart the AG

This must be done from only one server.

Type, or copy and paste the script into the PowerShell window.

```
Stop-ClusterResource $nameAGCluster  
Start-ClusterResource $nameAGCluster  
Start-ClusterGroup $nameAGCluster
```

Ensure that all three commands are successful.

```
PS C:\Windows\system32> Stop-ClusterResource $nameAGCluster
```

```
Name State OwnerGroup ResourceType  
-----  
-----
```

```
CC2K125ECEDB Offline CC2K125ECEDB SQL Server Availability Group
```

```
PS C:\Windows\system32> Start-ClusterResource $nameAGCluster
```

```
Name State OwnerGroup ResourceType  
-----  
-----
```

```
CC2K125ECEDB Online CC2K125ECEDB SQL Server Availability Group
```

```
PS C:\Windows\system32> Start-ClusterGroup $nameAGCluster
```

```
Name OwnerNode State  
-----  
-----
```

```
CC2K125ECEDB CC2K125ECEAA Online
```

Type, or copy and paste the commands into the PowerShell window

```
Get-ClusterResource $nameAGCluster  
Get-ClusterGroup $nameAGCluster
```

Ensure that both show the **State** as Online.

```
PS C:\Windows\system32> Get-ClusterResource $nameAGCluster
```

```
Name State OwnerGroup ResourceType  
-----  
-----
```

```
CC2K125ECEDB Online CC2K125ECEDB SQL Server Availability Group
```

```
PS C:\Windows\system32> Get-ClusterGroup $nameAGCluster
```

```
Name OwnerNode State
```

```
---- -
```

```
CC2K125ECEDB CC2K125ECEAA Online
```

## Configuration Checkpoint

Now that all of the prerequisites have been done, you are ready to install ECE. Before you continue, check that all of each item in the list has been completed.

- Both web servers have been deployed, Windows 2016 installed, and all desired Microsoft updates completed.
- Both collocated servers have been deployed, Windows 2016 and SQL Server 2016 Enterprise Edition installed, and all desired Microsoft updates completed.
- Distributed File System must be installed and the required directories for the ECE File server component created, a Domain Namespace and Replication group configured, and all permissions verified.
- Windows Server Failover Cluster must be installed and functional. You must a UNC share as the Quorum drive.
- SQL Server Availability Group must be enabled, a new Availability Group created, with a test DB added. While not in the scope of this document, failover for the Availability Group must be fully tested and either collocated server must be able to become the primary replica.

Before you continue, carefully read the ECE Installation Guide for the version of ECE and which corresponds to the deployment of Contact Center you have in your environment (UCCE or PCCE). Many of the install steps of ECE are the same for both UCCE and PCCE integrated systems, however, it is important that you follow the correct document as the configuration steps on the Contact Center side are quite different. PCCE is largely automated, but has different certificate requirements due to the use of SPOG (single pane of glass). UCCE has more prerequisite steps on the Contact Center side and is administered through the traditional methods. (Internet Explorer to the ECE server at, <https://ece.example.com/default>, etc.)

This document does not cover the install steps that are common to both standalone and HA installs such as the creation of the ECE Service account, the configuration of the Windows firewall rules, anti-virus/anti-malware scanner exclusion configuration, etc. nor does it give a step-by-step walk through of the install steps. Instead, the remainder of this document assumes that you are familiar with how to install ECE, have completed all of the pre-installation steps covered in the Enterprise Chat and Email Installation and Configuration Guide, and now have the ECE Fresh Install iso file mounted on all 4 servers and are ready to begin the install.

## Install ECE

The installation of ECE requires you to run setup five times. You run setup twice on the side-A collocated server, then one time each on the other three servers. The same name convention for the servers that is used in the product documentation is used for this document. For reference, here are the names and roles of each server along with the names that are used, (where names are shown) in the remainder of the document.

VM Identifier

VM Role

ECE Roles

VM Example

VM Example

|       |                          |   | Name          |           |
|-------|--------------------------|---|---------------|-----------|
| VM-1A | Side-A collocated server | File Server (DFS Node 1), Database (Availability Group Replica), Messaging, Services, Application | CC2K125ECEA A | 14.10.162 |
| VM-2A | Side-A web server        | Web Server  | CC2K125ECE WA | 14.10.162 |
| VM-1B | Side-B collocated server | File Server (DFS Node 2), Database (Availability Group Replica), Messaging, Services, Application | CC2K125ECEA B | 14.10.172 |
| VM-2B | Side-B web server        | Web Server  | CC2K125ECE WB | 14.10.172 |

**Note:** Before you begin the installation, validate and note which database server is the primary replica. You need to know this in order to complete the post-installation steps.

**Note:** ECE HA does not support SQL Server Authentication. You must use Integrated Authentication. Please ensure that you have completed the section of the pre-installation steps to properly configure SQL Server to allow Integrated Authentication to succeed.

## Step 1. Install ECE on VM-1A

### 1. Run setup.exe the first time.

This is the only server where you need to run setup twice. The first time, the File Server and Database Server components are installed.

At the **Installation Options** page, select **ONLY File Server** and **Database Server**, then select **Next >**. When prompted to enter the **File Server Directory/NAS Path**, enter the UNC path of the DFS share you created in the format **\\massivedynamic.com\ECE\_Root\ECE**. Fill out the next screens as required for your installation. When prompted for **SQL Server Database Authentication**, select **Integrated Authentication**. Be very careful to enter the correct information when you configure the databases. When you enter the **Server name** for any of the databases, you must use the fully-qualified name of the Listener. Example: **CC2K125ECEDB.MassiveDynamic.com**. The **Server Instance Name** can generally be left blank unless you have configured a named instance of SQL Server. The **Database Listen Port** is the port configured for the Listener. The **Datafile Path** is the location on the 300GB drive which you created for the databases. Example: **F:\MSSQL\DATA**. The **Reports Database SSIS Parameters** page must be completed as follows. **SSIS Datafile Path**– Location on the 50GB drive you have configured for SSIS. This is the directory configured in the pre-install steps. Example: **E:\ssis\_data**. **Domain User Name** – Username for the SQL Server Service account in the format of, DOMAIN\user. Example: **MASSIVE\SQLServerSvc**. **Domain Password** – Active Directory password for the selected user. The **Reports Database SSIS Catalog Parameters** page is the encryption password for the SSIS catalog. This information is required to complete the Post-Installation steps. The **Domain User Account Parameters** page is where you populate the username and password for the service account created to run ECE. After you provide this information, ECE install begins. As this install configures the File and Database components, this takes the longest amount of time. Please wait until it is complete, then continue.

### 2. Run setup.exe the second time.

The second time that you run setup.exe, the Messaging, Services, and Application components are installed on the side-A collocated server. At the **Installation Options** page, select **ONLY, Messaging Server, Application Server, Services Server**, then select **Next >**. When prompted to enter the **File Server Directory/NAS Path**, enter the UNC path of the DFS share you created in the format `\\massivedynamic.com\ECE_Root\ECE`. When prompted to enter the **Enterprise Chat & Email Home Directory**, enter the location on the 50GB drive you wish to use for ECE at run time. This directory must NOT be the same as the directory that is shared in the DFS. Example: `E:\ECE` Fill out the other pages as required. After you reach the summary screen and select **Finish**, ECE install begins.

## Step 2. Install ECE on VM-1B

In contrast to the collocated server on side A, you only need to run setup a single time on side B.

1. At the **Installation Options** page, select **ONLY, Messaging Server, Application Server, Services Server**, then select **Next >**.
2. When prompted to enter the **File Server Directory/NAS Path**, enter the UNC path of the DFS share you created in the format `\\massivedynamic.com\ECE_Root\ECE`.
3. When prompted to enter the **Enterprise Chat & Email Home Directory**, enter the location on the 50GB drive you wish to use for ECE at run time. This directory must NOT be the same as the directory that is shared in the DFS. Example: `E:\ECE`
4. Fill out the other pages as required.  
**Note:** Ensure that all configuration items such as **Context Root, Partition Name**, etc. match the side-A collocated server.
5. After you reach the summary screen and select **Finish**, ECE install begins.

## Step 3. Install ECE on VM-2A and VM-2B

The process to install ECE on VM-2A and VM-2B is quite straightforward. You need to run setup a single time.

1. At the **Installation Options** page, select **ONLY, Web Server**, then select **Next >**.
2. When prompted to enter the **Enterprise Chat & Email Home Directory**, enter the path on the 80GB drive you wish to use for ECE at run time. Example: `C:\ECE`
3. At the **Application Server Parameters**, provide this information Enter the **Application Server Name** as the fully-qualified name of the collocated server on the same side as the web server.  
Example:  
CC2K125ECEWA Web Server must point to the CC2K125ECEAA Application Server  
CC2K125ECEWB Web Server must point to the CC2K125ECEAB Application Server Enter the **Jetty HTTP Port** that you configured when you installed the collocated servers.
4. At the **IIS Web Site Parameters** page, select the **IIS Web Site Name** you wish to use for ECE. Generally this is **Default Web Site**.
5. Ensure that the **Context Root** and **Partition Name** match what is configured when you installed the collocated servers.
6. If you install the Web servers off of the domain, you must create a local username and password on each server to use when prompted for **Domain Username** and **Domain User Password**.



7. After you reach the summary screen and select **Finish**, ECE install begins. Once you have completed these steps, ECE is installed. Before you start the services though, there are several post-installation tasks which must be completed.

## Complete Post-Installation Tasks

To complete the installation of ECE, you need to do these steps. There is one step referenced in the documentation which must be completed in a different order based on the version of ECE you have installed.

### Step 1. Assign Permissions to ECE Directories

1. On both collocated servers, open the **Windows File Explorer**.
2. Navigate to the drive that contains the ECE Home directory. Example: **E:\**
3. **Right-Click** the ECE Home directory and choose **Properties**.
4. Select the **Permissions** tab, then select the **Edit** button.
5. In the permissions window that comes up, select the **Add...** button.
6. Enter the name of the service account you created to run ECE into the **Enter the object names to select** box. Example: **MASSIVE\ECESvc**
7. Select **OK** to return to the permissions window.
8. Ensure that the account you just added is selected in the list, then select the **Allow** checkbox beside **Full control**.
9. Select **OK** then **OK** again.

### Step 2. Start then Stop ECE Service on Collocated Servers

Before you run the ReportsDB utility, the ECE service must be started, then stopped on each collocated server. When the service starts the first time, ECE copies files from the DFS share to the ECE Home directory on the server. These files are required for the ReportsDB utility to run later in this process.

1. Log in to both collocated servers.
2. Open the **Windows Services Control Panel** and navigate to the **Cisco Service** and start the service.
3. Repeat this on the second collocated server.
4. Open **Task Manager**, select the **Details** tab and sort the processes by User name. Monitor until you see the processes start. There are 20-30 processes on one of the collocated servers and 9-10 processes on the second one. The total time to start all processes the first time may be close to 15 minutes.
5. Once you see that new processes have started in **Task Manager**, return to the **Services Control Panel** and stop the **Cisco Service**.
6. Monitor **Task Manager** again until all processes stop. The shutdown of ECE generally take 3-5 minutes. Subsequent service startup is faster as the files are already copied down.

### Step 3. Prepare Databases to Join the Availability Group

1. Open **SQL Server Management Studio** and connect to the Primary Node.



2. Change Recover model for each database. To do this via the GUI, do these steps. Expand **Databases** and do these steps on each of the three ECE databases. Right-click the database and choose **Properties**. Select the **Options** page in list on the left of the **Database Properties - <Databasename>** tab. In the drop-down next to **Recovery Model:**, select **Full**. Select **OK**. Repeat for each database. To do this via T-SQL, do these steps. Choose **New Query** in the tool bar. In the new query window, copy/paste or type these three commands. Change the database name as required.

```
ALTER DATABASE eGActiveDB SET RECOVERY FULL WITH NO_WAIT
ALTER DATABASE eGMasterDB SET RECOVERY FULL WITH NO_WAIT
ALTER DATABASE eGReportsDB SET RECOVERY FULL WITH NO_WAIT
```

Select **Execute** in the toolbar to run the query

3. Make a full backup of all three databases.

You can use either the GUI method or the T-SQL method to create this backup. Both methods are shown and assume that you already have **SQL Server Management Studio** open and that you used the default database names for ECE. Via GUI Right-click the **eGActiveDB** database and choose **Tasks > Back Up...** Check the **Back Up Database - eGActiveDB** box that comes up and ensure that the **Backup type:** is set to **Full** and that the **Destination** is **Disk**. Also ensure that the location shown is correct for your system. Use the **Add / Remove** buttons to make any necessary changes. Select **OK** and ensure that you see **The backup of database 'eGActiveDB' completed successfully**. Repeat for the **eGMasterDB** and **eGReportsDB** databases. Via T-SQL Select **New Query** in the tool bar. In the new query window, copy/paste or type these three commands. Ensure that you make any changes required for both database name and backup file location.

```
BACKUP DATABASE eGMasterDB
TO DISK = N'F:\MSSQL\Backups\eGMasterDB.bak'
WITH NAME = N'eGMasterDB-Initial Full Backup',
COMPRESSION, STATS = 25
GO
```

```
BACKUP DATABASE eGActiveDB
TO DISK = N'F:\MSSQL\Backups\eGActiveDB.bak'
WITH NAME = N'eGActiveDB-Initial Full Backup',
COMPRESSION, STATS = 25
GO
```

```
BACKUP DATABASE eGReportsDB
TO DISK = N'F:\MSSQL\Backups\eGReportsDB.bak'
WITH NAME = N'eGReportsDB-Initial Full Backup',
COMPRESSION, STATS = 25
GO
```

Select **Execute** to run this. Check the **Messages** tab to see a line similar to this for each of the three databases.

BACKUP DATABASE successfully processed 110986 pages in 8.153 seconds (106.350 MB/sec).

4. Make a transaction log backup of all three databases.

You need to make a Transaction Log backup of all three databases in order to join them to the Availability Group. Use one of the two methods shown to do this. Via the GUI. Right-click the **eGActiveDB** database and choose **Tasks > Back Up...** In the **Back Up Database - eGActiveDB** box verify each item below. The **Backup type:** is set to **Transaction Log** The **Destination** is **Disk** and the location shown is correct for your system Use the **Add / Remove** buttons to make any necessary changes. Select **OK**. Ensure that you see **The backup of database 'eGActiveDB' completed successfully**. Repeat for the **eGMasterDB** and **eGReportsDB** databases. Via T-SQL Select **New Query** in the tool bar. In the new query

window, copy/paste or type these three commands. Ensure that you make any changes required for both database names and file location.

```
BACKUP LOG eGMasterDB
TO DISK = N'F:\MSSQL\Backups\eGMasterDB.trn'
WITH NAME = N'eGMasterDB-Initial T Log Backup',
COMPRESSION, STATS = 25
GO
```

```
BACKUP LOG eGActiveDB
TO DISK = N'F:\MSSQL\Backups\eGActiveDB.trn'
WITH NAME = N'eGActiveDB-Initial T Log Backup',
COMPRESSION, STATS = 25
GO
```

```
BACKUP LOG eGReportsDB
TO DISK = N'F:\MSSQL\Backups\eGReportsDB.trn'
WITH NAME = N'eGReportsDB-Initial T Log Backup',
COMPRESSION, STATS = 25
GO
```

Select **Execute** to run this. Check the **Messages** tab to see a line similar to this for each of the three databases.

BACKUP DATABASE successfully processed 110986 pages in 8.153 seconds (106.350 MB/sec).

## Step 4. Restore Database Backup on Side-B Server

Before the databases can be added to the Availability Group, you first need to restore the backup on side B.

1. Copy the 3 .bak files and 3 .trn files that you created in steps 3 and 4 to the side-B collocated server. Ensure that you copy these files to the same location where they were on side A. For instance, if you followed the examples given, copy the databases to the F:\MSSQL\Backups folder on the side-B server.
2. Open **SQL Server Management Studio** and connect to the side-B server.
3. Select **New Query** in the tool bar.
4. In the new query window, copy/paste or type these commands. Ensure that you make any changes required for your system.

```
RESTORE DATABASE eGMasterDB
FROM DISK = N'F:\MSSQL\Backups\eGMasterDB.bak'
WITH NORECOVERY, STATS = 25
GO
```

```
RESTORE DATABASE eGActiveDB
FROM DISK = N'F:\MSSQL\Backups\eGActiveDB.bak'
WITH NORECOVERY, STATS = 25
GO
```

```
RESTORE DATABASE eGReportsDB
FROM DISK = N'F:\MSSQL\Backups\eGReportsDB.bak'
WITH NORECOVERY, STATS = 25
GO
```

```
RESTORE LOG eGMasterDB
FROM DISK = N'F:\MSSQL\Backups\eGMasterDB.trn'
WITH NORECOVERY, STATS = 25
GO
```

```
RESTORE LOG eGActiveDB
FROM DISK = N'F:\MSSQL\Backups\eGActiveDB.trn'
WITH NORECOVERY, STATS = 25
GO
```

```
RESTORE LOG eGReportsDB
FROM DISK = N'F:\MSSQL\Backups\eGReportsDB.trn'
WITH NORECOVERY, STATS = 25
GO
```

**Note:** Ensure that you use the WITH NORECOVERY option when you restore each database. This allows SQL Server to join the database to the Availability Group successfully in the next step.

5. Select **Execute** to run these queries. Review the **Messages** tab to see that all 6 RESTORE statements completed successfully.

**Note:** All three databases are listed with the word Restoring next to their name. This is expected.

## Step 5. Join Databases to the Availability Group

Now that the databases are restored on the side-B collocated server, add them to the AG.

1. Open **SQL Server Management Studio** and connect to the Primary Node.
2. Expand **Always On High Availability > Availability Groups**.
3. Right-click the Availability Group name you created and choose **Add Database...**
4. Select **Next >** until you see **Select Databases**.
5. All three ECE databases should be shown and the **Status** should be **Meets prerequisites**. Select the box beside each database, then select **Next >**. **Note:** The SSISDB must NOT be added to the Availability Group.
6. On the **Connect to Existing Secondary Replicas** screen, select the **Connect...** button beside the side-B server, then select **Connect** in the **Connect to Server** box. Select **Next >** to continue to the next page.
7. On the **Select Initial Data Synchronization** page, choose the option **Join Only**. Select **Next >** to continue to the next page.
8. On the **Validation** page, ensure that all checks are successful. If you receive any errors, select the error in the **Results** column, and take any necessary corrective action. Select **Next >** once all show green.
9. Review the **Summary** page, then choose **Finish** to join the databases to the Availability Group.
10. On the **Progress** page, select the **More details** button to monitor the specific steps. When you see all steps show a **Result of Success**, select **Close**.

## Step 6. Validate Availability Group

Once you have done these steps, open the Availability Group Dashboard used after you created the Availability Group to see that all databases are now added to the Availability Group and show synchronized with no data loss.

## Step 7. Run Reports DB Utility

Due to a defect in the 12.0 base release, the reportsDBUtility included on the install media does not work. If you installed 12.5 or higher, proceed with the next steps. If you installed 12.0, complete the next major section, **Patch ECE**, then return and complete the last three tasks in this section.

1. Copy the directory to the side-A collocated server. On a 12.5 or higher release, open the DVD drive, then navigate to the **Utilities** directory and copy the **ReportsDB Utility (SQL Server Always ON)** directory to the same drive where you have installed ECE. Example: **E:\ReportsDB Utility (SQL Server Always ON)**. On a 12.0 release, after you apply the latest ES in the **Patch ECE** section, open the location where you unzipped the ES, then navigate to the **Utilities** directory and copy the **ReportsDB Utility (SQL Server Always ON)** directory to the same drive where you have installed ECE. Example: **E:\ReportsDB Utility (SQL Server Always ON)**.
2. Update the batch file. In the directory you copied over, edit the **reportsdb\_utility.bat** file in notepad. Find the line that reads, **SET JAVA\_HOME=<JAVA\_HOME>** and replace the **<JAVA\_HOME>** with the local directory which is shared into DFS.  
Example: **SET JAVA\_HOME=E:\ECEFile\env\jdk** Save the file and exit notepad.
3. Update the .properties file

**Note:** Since this file is used by Java, certain characters need to be escaped. One of these is the \. Whenever a file location is referenced, the path must be escaped correctly. For example, E:\ssis\_data needs to be escaped as E:\\ssis\_data. The DFS share must be fully escaped. Pay close attention to the example. This holds true throughout the entire file. In the same directory, edit the **reportsdb\_utility.properties** file in notepad. Edit these lines

**ECE\_HOME\_DIR=C:\\ECE** – Update to the properly escaped DFS share. Example:  
**ECE\_HOME\_DIR=\\massivedynamic.com\\ECE\_Root\\ECEREPORTS\_DB\_SERVER\_NAME=** – Provide the fully qualified server name of the server which was the secondary replica server at install time. If you have performed a failover after install, ensure that you failover the Availability Group back to the original configuration. One way to tell is that the secondary replica generally does not have the SSISDB on it. Example:  
**CC2K125ECEAB.massivedynamic.comREPORTS\_DB\_LST\_PORT=** – Provide the Listener port. Typically this is 1433.  
**REPORTS\_DB\_INSTANCE\_NAME=** – If you installed the listener on a named instance, provide that instance name here. Otherwise, this can be left blank.  
**REPORTS\_DB\_NAME=** – Provide the name of the reports database. Example:  
**eGReportsDBACT\_DB\_SERVER\_NAME=** – Provide the fully qualified server name of the server which was the secondary replica server at install time. If you have performed a failover after install, ensure that you failover the Availability Group back to the original configuration. One way to tell is that the secondary replica generally does not have the SSISDB on it. ;Example: **CC2K125ECEAB.massivedynamic.comACT\_DB\_LST\_PORT=** – Provide the Listener port. Typically this is 1433.  
**ACT\_DB\_INSTANCE\_NAME=** – If you installed the listener on a named instance, provide that instance name here. Otherwise, this can be left blank.  
**ACT\_DB\_NAME=** – Provide the name of the active database. Example:  
**eGActiveDB** If present – **MAST\_DB\_NAME=** – Provide the name of the master database. Example: **eGMasterDB**  
**SSIS\_INSTALL\_PATH=** – Provide the path to the SSIS folder created on the secondary server. Example: **E:\\ssis\_data**  
**SSIS\_USER\_ID=** – Provide the SSIS Username that you gave when you set up ECE. Example:  
**MASSIVE\\SQLServerSvc**  
**SSIS\_USER\_PASSWORD=** – Provide the Active Directory password for the SSIS User which was given in the initial setup.  
**SSIS\_CATALOG\_PASSWORD=** – Provide the SSIS Catalog password chosen when

you installed ECE.If the field is not referenced in this list, then it can be safely left at its default setting or left blank.Save the file and exit notepad.

4. Run the batch file Open a new command prompt and change to the location where you copied the **ReportsDB Utility (SQL Server Always ON)** directory. Example: **cd e:\ReportsDB Utility (SQL Server Always ON)**Run the command exactly as shown. **reportsdb\_utility.bat createdBObjects**This can take several minutes to complete. Once the command prompt returns, open the Windows File Explorer and navigate to the same directory, then open the logs directory.Open the log file that ends with **ReportsDBUtil.log**. Example: **eg\_log\_CC2K125ECEAA\_ReportsDBUtil.log**Scroll to the bottom of the file and ensure that you see a line which contains this line.  
com.egain.platform.module.reportsdbutility.CreateReportsDB <@> main() <@>  
\*\*\*\*\* ReportsDB utility is executed successfully !!! \*\*\*\*\* <@>If you do not see the success output, review the the ReportsDBUtil.log file and other log files in the directory to determine the cause.

## Step 8. Fix SSIS Server Maintenance Job

When the SQL Server Integration Services is enabled, Microsoft creates a job in the SQL Server Agent jobs named **SSIS Server Maintenance Job**. Without any intervention, this job fails. Use these steps to resolve the issue that causes this failure.

1. Log in to both collocated servers.
2. Open **SQL Server Management Studio** and connect to the SQL Sever by the local server name.
3. Select **New Query** from the toolbar.
4. In the new query window, paste these T-SQL commands.

```
USE [SSISDB]
GO
```

```
GRANT EXECUTE ON [internal].[cleanup_server_execution_keys] TO
[##MS_SSISServerCleanupJobUser##]
GO
```

```
GRANT EXECUTE ON [internal].[cleanup_server_log] TO [##MS_SSISServerCleanupJobUser##]
GO
```

```
GRANT EXECUTE ON [internal].[cleanup_server_project_version] TO
[##MS_SSISServerCleanupJobUser##]
GO
```

```
GRANT EXECUTE ON [internal].[cleanup_server_retention_window] TO
[##MS_SSISServerCleanupJobUser##]
GO
```

5. Select **Execute** in the toolbar and monitor the **Messages** tab for this line.  
Commands completed successfully.
6. Repeat this on the other collocated server.

## Step 9. Schedule Database Backups

Database backups are important in any production system, but when ECE is installed in an HA configuration, they become vital to ensure that the product remains stable and that your disks do not become completely full. When a SQL Sever database is in Full recovery mode, different rules

apply to how the transaction log is managed. In a Simple recovery model database, the transaction log can be reused as soon as the data in it has been committed to the data file and there are no open transactions which reference the data. In a Full recovery model database however, the transaction log can only be reused after one of two things occurs.

1. A Full database backup – Once a full database backup has been completed, then the transactions in the transaction log are automatically committed into the data file(s) and therefore the log can be safely reused.
2. A Transaction log backup – This is a special backup which is only valid for Full or Bulk Logged recovery models. A full database backup is required before the first transaction log backup can occur, but after this, the transaction log can be backed up and the log space reused.

Because of this, you must carefully design your database backup plan. If backups are not done frequently enough, the transaction log continues to grow and, after time, fill up the entire disk. One possible backup plan is shown, but there are many others. This document does not give the specifics on how to configure the backups. Please consult Microsoft documentation or a qualified SQL Server expert for details.

Here are the definitions of some terms used.

#### Full Backup

- This backup type results in a single file that contains an the entire backup of a database. This file contains all information required to restore the database to the point-in-time at which the backup was made.
- To fully restore this backup, you simply need the backup file which corresponds to the last full backup.

#### Differential Backup

- This backup type contains the differences in the database since the last full backup. Since most databases grow at a fairly consistent rate, each differential backup file is quite a bit smaller than the Full backup.
- To fully restore the database, you need the file that contains the last Full database backup, plus the file that contains the last differential backup.

Note: SQL Server does not have any native concept of an incremental backup.

#### Transaction Log Backup

- This backup type contains the changes in the transaction log since the last backup. The last backup can be any one of the three backup types, Full, Differential, or Transaction Log. If performed on a regular basis, the size of the transaction log backup can be extremely small, sometimes only 1-2MB. Since the size is dependent on how busy the database is and when the last backup occurred, it is almost always better to do more frequent Transaction Log backups rather than fewer. Transaction log backups do allow you to restore a database to a point in time. If you know that data corruption happened at, for example 14:53:27.003 server time yesterday afternoon, you could restore the backup files in the correct order and choose to roll the database forward to 14:53:27.000. Any data after this time would be lost, but you would have a known good database.
- To fully restore the database, you need all of these:
- File that contains the last full backup
- File that contains the last differential backup
- ALL of the files that contain Transaction log backups made since either the last full or differential backup, whichever occurred last.

User Database – In Microsoft SQL Server, a user database is any database that is not required to run the server itself.

System Database – In Microsoft SQL Server, a system database is one of the 4 databases which the server requires in order to run, plus the distribution database if SQL Replication is configured. The four databases are, master, model, msdb, and tempdb. In SQL Server Management Studio, the system databases are in a folder named System Databases under the Databases folder node in the tree.

1. Full Backup - In this plan, all User databases are scheduled for a Full backup each Sunday morning at 01:30AM server time. The backups are compressed and the last 8 weeks of backups are retained on the server. A SQL Job is used to purge the SQL Backups older than 8 weeks.
2. Differential Backup – In this plan, all User databases are scheduled for a Differential backup every morning, with the exception of Sunday morning, at 01:30AM. The backups are compressed and the last 2 weeks of backups are retained on the server.
3. Transaction Log Backup – In this plan, all User databases are scheduled for Transaction Log backup that starts at 01:30AM and repeats every 1 minute. The backups are UNcompressed and the last 49 hours of backups are retained on the server. While every 1 minute can seem extreme, since this backup file size is based the rate of change of the transaction log since the last backup, the total size of the files over time remains roughly the same whether this is done ever 1 minute, 5 minutes, 30 minutes, or longer. If a backup is made every 1 minute however, the actual transaction log is allowed to be reused much more quickly and this, over time, reduces the overall space required to store both the database files and the backup files.

The details to implement this plan are outside the scope of this document. Please consult Microsoft SQL Server documentation for assistance.

## Step 10. Update Key Configuration Files

There are two files on each web server which generally need to be updated in a HA installation of ECE.

The first is the `ece_config.js` file that is used to load the Finesse gadget. At install, this file is created that contain the fully qualified host name of the web server. Since most HA ECE is accessed through a fully qualified name that is not a part of one server or the other, This file must be updated to ensure the proper functionality of the Finesse gadget.

The second file is not required to be updated, but it makes later changes the Finesse desktop layout much easier if it is updated.

**Tip:** Download and use a text editor such as Notepad++ to make these and other files on ECE much easier to edit. If you open the files in either Notepad or Wordpad you may see display issues and cause format corruption.

1. Log in to each web server.
2. Navigate to the ECE home directory.
3. In this directory, navigate to this path, `eService\templates\finesse\gadget\`.
4. Update the `ece_config.js` file. Navigate in to the `agent` directory. Locate the `ece_config.js` file and make a backup copy in a safe location. Open the current `ece_config.js` file in a text editor. Locate these two lines and update them to match your deployment.  
The `web_server_protocol` must be `https`, update if required.  
Update the `web_server_name` to match the fully qualified name that you allocated to use to

access ECE. Example: **ece.massivedynamic.com** var web\_server\_protocol = "https";var web\_server\_name = "CC2K125ECEWB.massivedynamic.com";

5. Review and, if desired, update the agent.xml file.

This update is not required. The contents of this file are designed to be copied, then pasted directly into the Desktop Layout in Finesse CAdmin. The file is not used directly by ECE, but if you update it with the correct configuration, it makes any required changes to Finesse at a later time much easier.

Return to the **gadget** directory, then navigate to the **layout** directory. Locate the **agent.xml** file and make a backup copy in a safe location. Open the current **agent.xml** file in a text editor. Locate and update the URL that is shown between the <gadget> and </gadget> tags to match the fully qualified name that you allocated to use to access ECE.

---

Once you have reached this point, ECE is fully installed and you are ready to log in to Partition 1 and Partition 0 to complete the setup. Please review the final notes section for other items which you may need to configure or check based on your deployment. There are many items which you may need to configure which are outside of the scope of this document. Some are listed in the final notes section, but this is by no means an exhaustive list. Please ensure that you review all relevant documentation for the most up-to-date configuration requirements.

## Patch ECE

It is recommended that ECE be kept as close as possible at the latest ES and ET patch level. This is especially important for issue resolution. All defects are fixed based on the latest patch release. You may be asked to apply the latest patch before a new defect can be confirmed. ECE does not currently support non-stop updates. This means that all patches must be applied while in a maintenance window when ECE can be completely stopped.

### Step 1. Prepare Servers to be Patched

1. **Stage Patch File** Download the patch and copy it to all four servers. Unzip the file, then carefully review the included readme.
2. **Stop ECE Processes** If ECE does not have any active email accounts or if all email accounts configured are for test purposes only, this step may safely be skipped. After you have run ECE in a production environment with email data for which you do not want to risk any loss, perform this step in order to test the ability to log in to ECE and even receive chats without the risk of data loss due to the retrieval of new emails by ECE. Since emails are deleted off the mail server when they are retrieved, this minimizes the possibility of loss of data should you need to uninstall the ES and restore the database backup.

**Tip:** The **system** partition is also known as **partition 0**. Open **Internet Explorer** and navigate to the ECE **system** partition. Example: <https://ece.massivedynamic.com/system> Log in with the **sa** account. In the **Consoles** screen, select the **System** console. Expand **Shared Resources > Services > Email**. Under this are two folder, **Dispatcher** and **Retriever**. Do these tasks in each folder. In the top half of the right-hand side of the page, select each process. In the bottom half of the right-hand side, select the drop-down arrow beside **Start type** and select **Manual**. Select the save button that is just above the **General** tab. Back in the top half, select the **Stop** button. Monitor the **State** column until it reads **Stopped**. Repeat with any other processes.

3. **Stop ECE** Log in to both collocated servers. Open the **Windows Services Control Panel** and



navigate to the **Cisco Service** and stop the service.Repeat this on the second collocated server.Open **Task Manager**, select the **Details** tab and sort the processes by User name. Monitor until all processes which are owned by the ECE Service account have stopped. There are be 35-40 processes on one of the collocated servers and 9-10 processes on the second one. The total time to stop all processes is generally 5-10 minutes.

## Step 2. Backup Servers

1. **Backup SQL Databases**Before you apply any patch to ECE or start any upgrade, a database backup of all three databases must always be made. When is in HA mode, ECE mandates that backups be scheduled on a regular basis. Even though the backup is scheduled, you must always make a separate backup before you start the patch or update installation so that you have an up-to-date copy. Open **SQL Server Management** studio and connect to the Listener.Select **New Query** in the toolbar.Copy and paste the SQL shown into the query window. Make any required changes to the path or database names.

```
BACKUP DATABASE eGActiveDB
TO DISK = N'E:\MSSQL\Backup\eGActiveDB_PrePatch.bak'
WITH NOFORMAT, NOINIT, NAME = N'eGActiveDB-Full Backup Before Patch',
SKIP, NOREWIND, NOUNLOAD, STATS = 25
GO
```

```
BACKUP DATABASE eGMasterDB
TO DISK = N'E:\MSSQL\Backup\eGMasterDB_PrePatch.bak'
WITH NOFORMAT, NOINIT, NAME = N'eGMasterDB-Full Backup Before Patch',
SKIP, NOREWIND, NOUNLOAD, STATS = 25
GO
```

```
BACKUP DATABASE eGReportsDB
TO DISK = N'E:\MSSQL\Backup\eGReportsDB_PrePatch.bak'
WITH NOFORMAT, NOINIT, NAME = N'eGReportsDB-Full Backup Before Patch',
SKIP, NOREWIND, NOUNLOAD, STATS = 25
GO
```

Select **Execute** in the toolbar.Monitor the **Messages** tab until all three database have completed backup. You should see lines similar to these after each successful backup. BACKUP DATABASE successfully processed 111346 pages in 9.877 seconds (88.072 MB/sec).

BACKUP DATABASE successfully processed 130283 pages in 9.629 seconds (105.704 MB/sec).

BACKUP DATABASE successfully processed 3533 pages in 0.298 seconds (92.611 MB/sec).

2. **Backup Key Files**Log in to each web server.Make a backup of any chat entry point directories you have customized.Make a backup of these files.

Note: Replace {install\_directory} the the ECE home directory on your system.

```
{install_directory}\eService\templates\finesse\gadget\agent\ece_config.js{install_directory}\eService\templates\finesse\gadget\layout\agent.xml
```

## Step 3. Install Patch

1. **Install patch on Side-A Collocated Server**Install the patch on the side-A collocated server in accordance with the readme file included with the patch.
2. **Install patch on Side-B Collocated Server**Install the patch on the side-B collocated server

in accordance with the readme file included with the patch.

3. **Install patch on Side-A Web Server** Install the patch on the side-A web server in accordance with the readme file included with the patch.

4. **Install patch on Side-B Web Server** Install the patch on the side-B web server in accordance with the readme file included with the patch.

## Step 4. Post-patch Validation

1. **Check and Update Key files** After you patch ECE, you must review the files that were backed up and merge any changes back in. You must not simply replace the new files with the backup copies as any changes made by the patch may be lost. Log in to each web server. Navigate to the ECE home directory. Compare these two files with the two that you made a back up of prior to the patch. Merge any changes into the new files.

Note: Replace {install\_directory} the the ECE home directory on your system.

{install\_directory}\eService\templates\finesse\gadget\agent\ece\_config.js {install\_directory}\eService\templates\finesse\gadget\layout\agent.xml

2. **Merge Chat Template Changes** When you apply a patch to ECE, you must review the documentation included with the patch. Each patch indicates the files which have changed in the chat templates. Merge the new files with the customized files from your system.

3. **Start ECE** Log in to both collocated servers. Open the **Windows Services Control Panel** and navigate to the **Cisco Service** and start the service. Repeat this on the second collocated server. Open **Task Manager**, select the **Details** tab and sort the processes by User name. Monitor until you see the processes start. There are 20-30 processes on one of the collocated servers and 9-10 processes on the second one. The total time to start all processes the after the install of a patch may be close to 15 minutes.

4. **Log in to ECE Web Pages** Open the URL that you use to access ECE administration pages. Verify that you are able to log in and that the processes and instances for all services have started.

If you installed the product with the default names for the two partitions, then the URLs are similar to these. Business Partition – <https://ece.massivedynamic.com/default> System

Partition – <https://ece.massivedynamic.com/system>

5. **Log in to Finesse and ECE Gadget** Log in to Finesse and load the ECE gadget. You should now be able to log in as an agent.

6. **Start ECE Processes** Once you have completed any tests that you wish to do, start the Processes that you stopped before the patch.

**Tip:** The **system** partition is also known as **partition 0**. Open **Internet Explorer** and navigate to the ECE **system** partition. Example: <https://ece.massivedynamic.com/system> Log in with the **sa** account. In the **Consoles** screen, select the **System** console. Expand **Shared Resources > Services > Email**. Under this are two folders, **Dispatcher** and **Retriever**. Do these tasks in each folder. In the top half of the right-hand side of the page, select each **process**. In the bottom half of the right-hand side, select the drop-down arrow beside **Start type** and select **Automatic**. Select the save button that is just above the **General** tab. Back in

the top half, select the **Start** button. Monitor the **State** column until it reads **Running**. Repeat with any other processes. Expand **Partitions > Default > Services > Email**. Under this are two folders, **Dispatcher** and **Retriever**. Do these tasks in each folder. In the top half of the right-hand side of the page, select each **instance**. In the bottom half of the right-hand side, verify that **Start type** is has **Automatic** selected. Select the **Start** button and monitor the **State** column until it reads, **Running**. Repeat with any other instances.

## Final Notes

Now that ECE is installed, there are several configuration items which you need to complete. Most of these are covered in the product documentation. A partial list of items which must be reviewed and configured per your site's needs is shown.

- Create a SSL certificate request, have this signed, and then assign this in Internet Information Services Manager to the website where you installed ECE
- Log in to the business partition and configure the **Web Server URL or Load Balancer URL** partition level setting to match the URL you allocated to use to access ECE  
**Note:** Ensure that you include the protocol when you configure this setting. Failure to do this may result in erratic system behavior. Example: <https://ece.massivedynamic.com>
- If you plan to use one of the secure methods to access your email server such as secure IMAP, POP3, or SMTP/ESMTP, and if your email server is an on-premises mail server that is signed with a non-public certificate authority, ensure that you import the appropriate certificates into the shared keystore on the collocated server.
- If you plan to configure Single Sign-On (SSO), ensure that you import the appropriate certificates from your Cisco IDS server into the shared keystore on the collocated server  
**Note:** All certificates must be imported into the keystore located in the Shared Directory, in the \env\jdk folder.
- Configure the load balancer for your environment.

It is outside of the scope of this document to provide specific guidance on load balancer configuration. Cisco does not recommend any specific load balancer. There are, however, several very specific configuration requirements which must be followed exactly to ensure proper system functionality. The most critical of these are as follows. The load balancer should be configured in a way that only one-half of the web servers are used at any time. Ideally, these should all be located in the same datacenter. For the 400-agent deployment, this means that only one of the two web servers should be active. The load balancer must keep all connections sticky via cookie insert. Since only one of the two web server should be used at a time in the 400-agent deployment, it is less critical that the cookie insert method be used. In the 1500-agent deployment however, you must use cookie-insert to maintain sticky sessions. The load balancer should perform regular health checks on the server to ensure availability. It is important to note that ECE does have some error handling built into the web server. If the back-end application server is down or offline, the web server does not show a normal html error page. For this reason, ensure that the health check that you choose monitors the content of the web page and not simply the HTML return code.

There are some special considerations when you integrate with a Packaged Contact Center Enterprise (PCCE) solution. PCCE does almost all management through the CCE Administration page which is also referred to as the single pane of glass (SPOG). When ECE is to be integrated with a PCCE system, the only items which should be configured via the classic ECE web pages are these.

- Partition Administrator Single Sign-on configuration  
Note, you must configure this even if you do not plan use agent or supervisor SSO.
- In addition to the changes to the ece\_config.js, covered in the post-installation steps, there is a similar file that is used to load the ECE gadget in SPOG. You can find this under the ECE home directory on each web server at this location, **eService\templates\finesse\gadget\spog**. Edit spog\_config.js and update the parameter, var web\_server\_name to match the fully qualified name you enter when add the ECE web server to the PCCE Inventory.
- Ensure that you import the SSL certificate that is assigned to ECE to the keystore on all Admin Workstations, then restart the Apache Tomcat Service before you attempt to open the ECE gadget.

It is recommended that you download several tools and keep them on the ECE Servers. These make it far easier to troubleshoot and maintain the solution over time.

- A text editor such as Notepad++
- A archive tool such as 7-Zip
- One of the many Tail for Windows programs  
A few examples are: Baretail – <https://www.baremetalsoft.com/baretail/>Tail for Win32  
– <http://tailforwin32.sourceforge.net/>